

**USE CASE:**

A client is going through the self-registration process and will receive the passcode to login via SMS message. In this example, I was using CLICKATELL.

Clickatell offers two different accounts. Make sure to have a developer account. Standard account does not allow to have access to the API

<https://www.clickatell.com/clickatell-products/online-products/sms-gateway-developers-central/>

**Login**

Which product would you like to log in to? Don't have an account? [Sign up here](#)

**Communicator2**  
Send bulk SMS via the internet. No programming needed.

**Developers' Central**  
Reliable, scalable, customisable.  
Integrates with your system via APIs.

make sure you have  
Developers' Central  
account

What is your username? \*

What is your Client ID? \*

What is your password? \* [Forgot your password?](#)

## Clearpass Guest -> Configuration -> SMS Services -> Gateway

Home » Configuration » SMS Services » Gateways

### Create SMS Gateway

Use this form to create a new SMS gateway.

| SMS Gateway Configuration |  |
|---------------------------|--|
| * SMS Gateway:            | Clickatell<br><small>Select the SMS gateway you have service with.</small>   |
| <b>Service Settings</b>   |  |
| Display Name:             | RBE Clickatell SMS Gateway<br><small>The name for this service handler. This will be displayed to operators using the system.</small>  |
| * Service Username:       | rbemsel<br><small>Your authorization username for the SMS service provider.<br/>Note, if you are using ClearPass Guest SMS Service and have entered your ClearPass Subscription ID, the username and password fields should be left blank.</small> |
| * Service Password:       | *****<br><small>Your authorization password for the SMS service provider.</small>  |
| Confirm Password:         | *****<br><small>Your authorization password for the SMS service provider.</small>  |
| API ID:                   | 1234567<br><small>An optional API ID, if required by the SMS provider.</small>   |
| SMS Source Address:       | <br><small>Set the originator address of sent SMS messages.<br/>This may be a phone number or short string, depending on the provider.</small>   |

Home » Configuration » SMS Services » Gateways

### SMS Gateways

Use this list view to define and edit SMS gateways.

| Name                       | Service Name                | Credits |
|----------------------------|-----------------------------|---------|
| ClearPass Guest SMS        | ClearPass Guest SMS Service | 191     |
| RBE Clickatell SMS Gateway | Clickatell                  | 393.500 |

2 gateways Reload Show all rows

You should send yourself a test message out of the Gateway configuration to make sure SMS Gateway is communicating correctly

| Name                       | Service Name                | Credits |
|----------------------------|-----------------------------|---------|
| ClearPass Guest SMS        | ClearPass Guest SMS Service | 191     |
| RBE Clickatell SMS Gateway | Clickatell                  | 393.500 |

Edit Duplicate Delete Make Default Send SMS

2 gateways Reload Show all rows

#### New SMS Message

\* Recipient: +4917 12345678  
Enter the mobile telephone number of the recipient in international format.

\* Message: This is my test message out of Clearpass via Clickatell  
105 characters left  
Enter the message to send (maximum 160 characters).

Send Message Cancel

Telekom.de 09:09

[← Nachrichten +45 609910233](#) [Details](#)

Nachricht  
Heute, 09:09

This is my test message out of Clearpass via Clickatell

Nachricht  Senden

Ok Yes No

Q W E R T Y U I O P  
A S D F G H J K L  
Z X C V B N M  
123 space return